


## Spectrum Monitor (waterfall chart) in EasySpectrum software

December 18, 2018


SIGLENT EasySpectrum software includes a spectrum monitor mode that shows a waterfall chart of successive scans. This can be useful if you are observing a carrier signal for drift as well as comparing successive spectral scans.

To enable the spectrum monitor:


1. Download EasySpectrum. Here is a link to the [EasySpectrum Getting Started Guide](#)
2. Connect your SIGLENT analyzer to the controlling computer
3. Open the EasySpectrum software
4. Right-click to select the spectrum analyzer from the list (USB connection) or enter the LAN address and choose Monitor Mode



5. Configure the analyzer to view the span of interest
6. Select MEAS, open the drop-down box, and select Spectrum Monitor



7. Now, successive scans will be shown building up from the bottom of the display as shown:





### **North American Headquarters**

SIGLENT Technologies America, Inc  
6557 Cochran Rd Solon, Ohio 44139  
Tel: 440-398-5800  
Toll Free: 877-515-5551  
Fax: 440-399-1211  
[info@siglent.com](mailto:info@siglent.com)  
[www.siglentamerica.com/](http://www.siglentamerica.com/)

### **European Sales Offices**

SIGLENT TECHNOLOGIES EUROPE GmbH  
Staetzlinger Str. 70  
86165 Augsburg, Germany  
Tel: +49(0)-821-666 0 111 0  
Fax: +49(0)-821-666 0 111 22  
[info-eu@siglent.com](mailto:info-eu@siglent.com)  
[www.siglenteu.com](http://www.siglenteu.com)

### **Asian Headquarters**

SIGLENT TECHNOLOGIES CO., LTD.  
Blog No.4 & No.5, Antongda Industrial Zone,  
3rd Liuxian Road, Bao'an District,  
Shenzhen, 518101, China.  
Tel: + 86 755 3661 5186  
Fax: + 86 755 3359 1582  
[sales@siglent.com](mailto:sales@siglent.com)  
[www.siglent.com/ens](http://www.siglent.com/ens)